

Posh Patterns

by
Jackie's Designs™



Melynda

This pattern copyright is for home use only
Resale of finished product is prohibited
Copyright © 2008 Jackie's Designs All rights reserved.
pattern 020

CUT AND SUPPLY LIST FOR MELYNDA:

1. You will need 2 panels 1 of fabric body cut 12 1/4" x 9" and 1 for the lining 12 1/4" x 9"
2. Cut 2 of light weight fusible interfacing 12 1/4" x 9"
3. 2 strips of double fold bias tape store purchase, each cut at 25" long
(If you do not want to use bias, you can use cording or ribbon.)
4. Plastic insert for bottom of bag for support, cut 1/2" smaller then the pattern supplied.
5. For draw string casing cut 2 strips of fabric, 1 1/2" x 6"

CONSTRUCTION:

1. Cut 2 from the circle pattern given .
2. Using your cut panels, please fuse the interfacing to the wrong side of the bag body and the lining panels.
3. Using the bag body panel fold in half long wise right sides facing each other and sew using a 3/8" seam allowance.



4. With the panel remaining wrong side facing you, evenly distribute the bottom edge of the panel lining up the raw edges of the circle and bottom edge, pin to secure. Be sure the right sides are facing each other, bag body panel and bag bottom.
See image below.



Sew in place using a 3/8" seam allowance. Turn right side facing you, press your bottom flat and seams.

LINING CONSTRUCTION:

1. Use the same instructions for the bag body to make the lining, excluding turning right side facing you.


HANDLE CONSTRUCTION:

1. Using the cut Bias tape, sew them closed but using a single machine stitch up the center of the Bias tape.
2. Tie your ends. Set aside for later.

COMPLETION OF WRISTLET:

CASING CONSTRUCTION:

1. Using your cut panels for the draw string casing. With wrong side facing you, press each long raw edge in towards the center of the casing.
2. Next fold each press each short end of the casing 1/2" towards the center.
3. Using the bag body, center the casing on one side of the bag 2" from the top. Pin in place.



Sew only the long ends of the casing, top and bottom. Repeat for the other side. Be sure the other casing is even distributed on the opposite side. Use a 1/8" seam allowance.



4. Once complete press the top edge of the lining and bag body top edge 1/2", press facing wrong side of the fabric.
5. Slip lining inside the bag, line your pressed edge and the side sewn seam. Pin to secure.
6. Sew in place using a 3/8" seam allowance.
7. Using a safety pin attach to end of your binding slip into the right cavity casing and come out of the other casing right side, till ends meet each other. Slip knot those ends together. Using the other Bias tape attach safety pin and insert on the left side of the first casing you went through, then come out through the other left side casing meeting the ends. Slip knot those together. You now have handles on each side, right and left. Pull tie to close bag.
Bag Complete.



Melyenda Wristlet
Posh Patterns

Cut 1 of bag body
Cut 1 of lining